

# Linux: ip address

Setting up a network interface with a static address in Debian distributions

To set up a network interface with a static address in Debian, modify the configuration file `/etc/network/interfaces`. Here are the steps to follow.

## Step 1: Edit the configuration file

Open a terminal and edit the `/etc/network/interfaces` file using a text editor such as nano or vim. Here is an example of using nano:

```
sudo nano /etc/network/interfaces
```

## Step 2: Adding a static configuration

Add the configuration for the network interface in the file. Below is an example for interface `eth0`, which will get the IP address `192.168.1.100` with a subnet mask of `255.255.255.0` and a default gateway of `192.168.1.1`.

```
# Ustawienia interfejsu Ethernet
auto eth0
iface eth0 inet static
    address 192.168.1.100
    netmask 255.255.255.0
    gateway 192.168.1.1
    dns-nameservers 8.8.8.8 8.8.4.4
```

Parameters

- `address`: The actual static IP address you want to assign to the interface.
- `netmask`: The subnet mask that is used for the local network.
- `gateway`: The IP address of the gateway (router) through which communication with other networks takes place.
- `dns-nameservers`: The addresses of the DNS servers that will be used for name resolution.

## Step 3: Save changes and exit

If you are using nano, press `CTRL + X`, then `Y` and `Enter` to save your changes and exit the editor.

## Step 4: Restart the web interface

To apply the new settings, restart the web interface. Use the following command:

```
sudo ifdown eth0 && sudo ifup eth0
```

If you are using a system where ifupdown can only be handled by systemd, you can also use:

```
sudo systemctl restart networking
```

## Step 5: Check the configuration

To ensure that the interface has been successfully configured, use the command:

```
ip a
```

This command will display the configurations of all interfaces, including the assigned IP address.

By setting a network interface statically, you ensure that it will always have the same IP address, which is particularly useful for servers and systems that require stability in network communication.

# Setting up a DNS server

Correct configuration of the DNS (Domain Name System) is essential for proper use of the Internet. To do this, you need to edit the two main configuration files:

`/etc/host.conf`: Defines how the name resolution function works.

Example file contents:

```
order hosts,bind
multi on
```

Sets that local host files will be searched first, followed by remote DNS servers.

`/etc/resolv.conf`: Contains the addresses of the DNS servers that will be used to resolve domain names.

Example of file:

```
nameserver 8.8.8.8
nameserver 8.8.4.4
```

This sets Google's DNS servers as default.

# For ubuntu systems

Netplan is a network configuration tool for Ubuntu systems, introduced in versions 17.10 and later. It allows simple configuration of network interfaces and their settings.

## Edit the configuration file:

The netplan configuration is stored in YAML files in the `/etc/netplan/` directory. They can be edited with a text editor, such as:

```
sudo nano /etc/netplan/01-netcfg.yaml
```

Example file content for a static IP address:

```
network:
  version: 2
  ethernets:
    eth0:
      addresses:
        - 192.168.1.100/24
      gateway4: 192.168.1.1
      nameservers:
        addresses:
          - 8.8.8.8
          - 8.8.4.4
```

## Application of changes:

After editing the file, save the changes and exit. Then примените the configuration using the command:

```
sudo netplan apply
```

## Check configuration:

To ensure that the network interface is configured correctly, use:

```
ip a
```

## Notes

- **YAML format:** Remember to use correct YAML formatting, especially with regard to indentation.
- **Debugging:** In case of errors, you can use the `sudo netplan try` command, which allows you to test your changes before applying them permanently.

Netplan simplifies network configuration in Ubuntu by offering a flexible approach to connection management.